

.iniedit file specification

It is a normal .ini file with the followings sections and fields:

[FILE]
Filename
New
SectionCount

[SECTION_XX]
Name
Description
FieldCount

[FIELD_XX_YY]
Name
Description
Type
Min
Max
Values
Dispvalues
Mandatory
DefaultValue

SECTIONS

FILE	
FileName	Name of the file (.ini, .cfg) that will be created/opened and has this configuration file.
New	Yes/No. Yes: If file does not exist, the application will create it. No: If field does not exist, the application will not create it.
SectionCount	Number of sections "SECTION_XX"

SECTION_XX

XX	Numeric section Id starting by "00".
Name	Name of the section.
DescriptionXX	Description of the section. XX: Numeric description id starting by "00".
Dynamic	Yes/No. Specifies if is a Dynamic Seccion. Dynamic sections has one description Field
ItemCountFieldName (*)	The name of the section counter in a dynamic section. Ex: "Counter "
ItemIndexStart (*)	Numeric starting id for the field name. Ex: ItemIndexStart = 1 and the field name is "File": File01 = File02 = ... FileXX =
ItemMax (*)	The maximum number of items.
ItemNew (*)	Yes/No. Specifies if the user can add new items.
ItemDelete (*)	Yes/No. Specifies if the user can delete items.
FieldCount	Number of fields in this section.

(*) only for Dymamic section

FIELD_XX_YY

XX	Numeric section Id starting by "00".
YY	Numeric field Id starting by "00".
Name	Name of the field
DescriptionXX	Description of the field. XX: Numeric description id starting by "00".
InputType	The Following input types are valid: IT (Text) VS (Values Selection) VI (Values Input) D (Display Values) FD (Folder Name) FL (File Name) IN (Numeric) The <i>Values</i> field is used if InputType is VS,VI or D . The <i>DispValues</i> field is used if InputType is D.
Validation	A set of data types separated by commas. The Following types of data are valid: ALNUM Alphanumeric (A - Z, a - z, or 0 - 9) ALPHA Alphabetic (A - Z or a - z) ASCII ASCII character (0x00 - 0x7F) CNTRL Control character (0x00 - 0x1F or 0x7F) CSYM Letter, underscore, or digit CSYMF Letter or underscore DIGIT Decimal digit (0 - 9) GRAPH Printable character except space LOWER Lowercase letter (a - z) PRINT Printable character including space (0x20 - 0x7E) PUNCT Punctuation character SPACE White-space character (0x09 - 0x0D or 0x20) UPPER Uppercase letter (A - Z) XDIGIT Hexadecimal digit (A - F, a - f, or 0 - 9) Ex: DIGIT,PUNCT
Min	If Validation is IN, specifies minimum number in the field. If Type is not IN, specifies the minimum characters in the field.
Max	If Valitacion is IN, Max specifies maximum numer in the field.

	If Type is not IN, specifies the maximum characters in the field.
Values	A set of values separated by commas. If <i>InputType</i> is VI, the user can enter a new value or select it from the list. <i>InputType</i> field must be VS or VI
DispValues	Display Values. A set of values separated by commas associated with <i>Values</i> field. Field <i>Values</i> is required. <i>Type</i> field must be D
Mandatory	Yes/No. Specifies if the field is mandatory. If it is a mandatory field, it can not be empty.
DefaultValue	A default value. The application assigns this value when the file is created.
Help	Help of the field
AutoRecord	Yes/No Specifies if field is auto-save.
HiddenField	Yes/No Specifies if it is a hidden field. If it is a hidden field, it cannot be filled by the user in the IniEditor Application.

Examples

1)

WTn52_88xx.Iniedit:

[FILE]

Filename = WTn52_88xx.pckg
New = yes
SectionCount = 3

[SECTION_00]

Name = package
Description = Information about package
FieldCount = 5

[SECTION_01]

Name = info
Description =
FieldCount = 4

[SECTION_02]

Name = application
Description =
FieldCount = 2

;Section 00

[FIELD_00_00]

Name = type
Description = package type
Type = T
Min = 1
Max = 1
Values = A,C
Mandatory = Yes
DefaultValue = A

[FIELD_00_01]

Name = id
Description = package id
Type = A
Min = 5
Max = 20
Mandatory = Yes
DefaultValue = 0

[FIELD_00_02]

Name = version
Description = package version
Type = A
Min = 5
Max = 20
Mandatory = Yes
DefaultValue = 1-0-0

[FIELD_00_03]

Name = name
Description = package version
Type = A
Min = 4
Max = 30
Mandatory = Yes
DefaultValue =

[FIELD_00_04]

Name = filelist
Description = name of the file list
Type = T
Min = 1
Max = 20
Mandatory = No
DefaultValue =

;Section 01

[FIELD_01_00]

Name = description
Description =
Type = T
Min = 0
Max = 100
Mandatory = No
DefaultValue =

[FIELD_01_01]

Name = platform
Description =
Values = WinCe400, WinCe410, WinCe420
DispValues = Windosw CE 4.00, Windows CE 4.10, Windows CE 4.20
Mandatory = Yes
DefaultValue = WinCe400

[FIELD_01_02]

Name = model
Description = model name
Values = PPT8800, PDT8100, MC9000, CK30
Mandatory = Yes
DefaultValue = PPT8800

[FIELD_01_03]

Name = vendor
Description = vendor name
Values = SYMBOL, INTERMEC
Mandatory = No
DefaultValue =

;Section 02

[FIELD_02_00]

Name = startexe
Description = name of the executable file
Type = T
Min = 1
Max = 30
Mandatory = Yes
DefaultValue =

[FIELD_02_01]

Name = icon
Description = name of the icon file
Type = T
Min = 1
Max = 30
Mandatory = No
DefaultValue =

2)

Sample of _WTnCE.cfg

```
// Local PDT Terminal options
[TERMINAL]
KeyClick=No // Keys click
PwdWConf=234 // WTn Config Pwd
PwdExit=307 // Exit to DOS Pwd
TaskBar=No // Enable the task bar (up)
CommandBar=Yes // Enable the command bar (down)
SIPPanel=Yes // Enable the button for the sip
ScrollBar=Yes // Enable the scrolls bars of the telnet window (not yet implemented)
Language=EN // French (FR), English (EN) and Spanish (ES)
```

_WTnCE.Iniedit:**[FILE]**

Filename = _WTnCE.cfg
New = yes
SectionCount = 1

[SECTION_00]

Name = TERMINAL
Description = Local PDT Terminal options
FieldCount = 8

[FIELD_00_00]

Name = KeyClick
Description = Keys click
Values = Yes,No
Mandatory = Yes
DefaultValue = No

[FIELD_00_01]

Name = PwdWConf
Description = WTn Config Pwd
Type = N
Mandatory = Yes
DefaultValue = 234
HiddenField = Yes

[FIELD_00_02]

Name = PwdExit
Description = exit to DOS Pwd
Type = N
Mandatory = Yes
DefaultValue = 307
HiddenField = Yes

[FIELD_00_03]

Name = TaskBar
Description = Enable the task bar (up)
Values = Yes, No
Mandatory = No
DefaultValue = No

[FIELD_00_04]

Name = CommandBar
Description = Enable the command bar (down)
Values = Yes, No
Mandatory = No
DefaultValue = Yes

[FIELD_00_05]

Name = SIPPanel
Description = Enable the button for the sip
Values = Yes, No
Mandatory = No
DefaultValue = Yes

[FIELD_00_06]

Name = SIPPanel
Description = Enable the scrolls bars of the telnet window
Values = Yes, No
Mandatory = No
DefaultValue = Yes

[FIELD_00_07]

Name = Language
Description = French (FR), English (EN) and Spanish (ES)
Values = FR,EN,ES
DispValues = French, English, Spanish
Mandatory = Yes
DefaultValue = EN